

HIMatrix[®]**F**

Release Notes







All of the HIMA products mentioned in this manual are trademark protected. Unless noted otherwise, this also applies to other manufacturers and their respective products referred to herein.

HIQuad[®], HIQuad[®]X, HIMax[®], HIMatrix[®], SILworX[®], XMR[®], HICore[®] and FlexSILon[®] are registered trademarks of HIMA Paul Hildebrandt GmbH.

All technical specifications and notes in this manual have been written with great care and effective quality assurance measures have been implemented to ensure their validity. For questions, please contact HIMA directly. HIMA appreciates any suggestion on which information should be included in the manual.

Equipment subject to change without notice. HIMA also reserves the right to modify the written material without prior notice.

All the current manuals can be obtained upon request by sending an e-mail to: documentation@hima.com.

© Copyright 2019, HIMA Paul Hildebrandt GmbH All rights reserved.

Contact

HIMA Paul Hildebrandt GmbH P.O. Box 1261 68777 Brühl, Germany

Fax: +49 6202 709-107 E-mail: info@hima.com

Phone: +49 6202 709-0

| Document designation | Description |
|-----------------------------------|---|
| HI 800 782 D, Rev. 1.01 (1938) | German original document |
| HI 800 783 E, Rev. 1.01.00 (1938) | English translation of the German original document |

Release Notes Table of Contents

| Table of | of Contents | |
|----------|--|----|
| 1 | HIMatrix Operating System V15/V20 | 5 |
| 2 | New Functions | 6 |
| 3 | Firmware Improvements | 7 |
| 4 | Firmware Restrictions | 8 |
| 4.1 | Upgrading from a Previous Version | 9 |
| 4.1.1 | Upgrade from V13.x/V18.x to V15/V20 | 9 |
| 4.1.1.1 | Upgrading the HIMatrix system to V15.x/V20.x | 9 |
| 4.2 | References | 9 |
| 4.3 | Zstandard License Conditions | 10 |
| | Appendix | 11 |
| | Index of Tables | 11 |

HI 800 783 E Rev. 1.01.00 Page 3 of 13

1 HIMatrix Operating System V15/V20

The new versions only support devices with enhanced performance:

- F30 03
- F35 03
- F60 CPU 03

This main chapter describes the improvements and new functions of the following operating system versions (V15/V20):

| OS version | File name | Description |
|------------|---------------------------|---|
| V15.8 | L3CPU_HA1_L3_OS_V15.8.ldb | Safety-related CPU operating system for F30 03, F35 03 and F60 CPU 03 controllers |
| V20.6 | L3COM_HA1_L3_OS_V20.6.ldb | COM operating system for F30 03, F35 03, F60 CPU 03 controllers |

Table 1: Modified Operating System Versions

HI 800 783 E Rev. 1.01.00 Page 5 of 13

2 New Functions Release Notes

2 New Functions

MultiForcing

This new access mode allows up to 5 users to write force data (force values and force switches) for global variables.

The access permission can be denied or granted using the enable switch in the project during a download or online, and using a system variable at runtime.

Modbus slave V2

Up to 20 TCP connections to one Modbus master can now be configured for Modbus slave V2. The total number of TCP connections to all the masters may not exceed 20. The number of currently used TCP connections to a Modbus master, is displayed in the online view.

Page 6 of 13 HI 800 783 E Rev. 1.01.00

3 Firmware Improvements

- The configuration download and reload have been optimized so that a significant time saving can be expected in most cases, especially in conjunction with larger projects.
- The following commands require *Administrator* access:
 - Resetting the module factory settings.
 - Changing the mono-redundant start-up switch.

Commands that stop or change the system, require at least Write access:

- Transition from RUN to STOP.
- Stop of a user program.
- Stop of system operation.
- Transition to Test Mode and Single Cycle.
- Reload, despite set ReadOnly system variable.

Commands that maintain the system in operation require at least *Operator* access:

- All force commands, despite set ReadOnly system variable.
- P2P statistics reset.

The changed permissions are only active if all CPUs in system operation are upgraded to V11.

HI 800 783 E Rev. 1.01.00 Page 7 of 13

4 Firmware Restrictions Release Notes

4 Firmware Restrictions

 In very seldom cases, if one or more communication protocols such as Modbus or ComUserTask are used under load control and the controller or COM module change from RUN to STOP, the COM module may reboot.

Restriction concerning the reload licenses:

If only a demo license is available to load a feature required by a module, it may occur that the feature is not updated properly when a reload with a regular license is performed. The message displayed in the license management of the CPU module indicates that a regular license is available, but a demo license is being used.

This behavior occurs when the module itself is not subject to reload or cold reload. The new license is only used and properly reported after a new restart, reload or cold reload of the module.

Page 8 of 13 HI 800 783 E Rev. 1.01.00

Release Notes 4 Firmware Restrictions

4.1 Upgrading from a Previous Version

4.1.1 Upgrade from V13.x/V18.x to V15/V20

Only processor and communication operating system versions that were released together can be used together.

The operating system of processor and communication modules can only be upgraded in the STOP state.

When upgrading the operating systems, HIMA recommends upgrading the associated OS loaders as well.

4.1.1.1 Upgrading the HIMatrix system to V15.x/V20.x

 $\begin{tabular}{ll} \hline 1 & The order described below must be absolutely observed! \\ \hline \end{tabular}$

- 1. Stop the resource if still in RUN.
- 2. In the Hardware Editor online view, connect to the communication module (system login) and upgrade the OS loader to V18.x.
- 3. Upgrade the communication operating system to V20.x.
- 4. Connect to the processor module by logging in to the system and upgrade the OS loader to V11.x.
- Connect to the processor module and upgrade the processor operating system to V15.x. The resource reboots.

The upgrade of the HIMatrix system to V15.x/V20.x is completed.

4.2 References

- HIMatrix system manual, document number HI 800 141 E
- HIMatrix safety manual, document number HI 800 023 E
- Communication manual, document number HI 801 101 E
- HIPRO-S V2 manual, document number HI 800 723 E
- ISOfast manual, document number HI 801 465 E

HI 800 783 E Rev. 1.01.00 Page 9 of 13

4 Firmware Restrictions Release Notes

4.3 Zstandard License Conditions

The CPU operating systems contain the *Zstandard* decompression algorithm provided with the following license conditions:

BSD License

For Zstandard software

Copyright (c) 2016-present, Facebook, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name Facebook nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Page 10 of 13 HI 800 783 E Rev. 1.01.00

Release Notes Appendix

Appendix

Index of Tables

Table 1: Modified Operating System Versions

5

HI 800 783 E Rev. 1.01.00 Page 11 of 13

Release Notes

HI 800 783 E

For further information, please contact:

HIMA Paul Hildebrandt GmbH

Albert-Bassermann-Str. 28 68782 Brühl, Germany

Phone +49 6202 709-0 Fax +49 6202 709-107 E-mail info@hima.com

Learn more about HIMatrix online:

https://www.hima.com/en/products-services/himatrix/