

# **HIQuad<sup>®</sup>X**

**Release Notes V13.2** 



All of the HIMA products mentioned in this manual are trademark protected. Unless noted otherwise, this also applies to other manufacturers and their respective products referred to herein.

HIQuad®, HIQuad®X, HIMax®, HIMatrix®, SILworX®, XMR®, HICore® and FlexSILon® are registered trademarks of HIMA Paul Hildebrandt GmbH.

All of the technical specifications and information in this manual were prepared with great care and effective control measures were employed for their compilation. For questions, please contact HIMA directly. HIMA appreciates any suggestion on which information should be included in the manual.

Equipment subject to change without notice. HIMA also reserves the right to modify the written material without prior notice.

All the current manuals can be obtained upon request by sending an e-mail to: documentation@hima.com.

© Copyright 2020, HIMA Paul Hildebrandt GmbH All rights reserved.

## Contact

HIMA Paul Hildebrandt GmbH P.O. Box 1261 68777 Brühl, Germany

Fax: +49 6202 709-107 E-mail: info@hima.com

Phone: +49 6202 709-0

Document designation	Description		
HI 803 244 D, Rev. 1.00 (2021)	German original document		
HI 803 245 E, Rev. 1.00.00 (2024)	English translation of the German original document		

Release Notes Table of Contents

Table	of Contents	
1	HIQuad X Operating System Version V13.2	5
2	New Functions	6
3	Firmware Improvements	7
4	Firmware Restrictions	8
5	References	9
5.1	Zstandard License Terms	9
5.2	Apache License	9
	Appendix	11
	Index of Tables	11

HI 803 245 E Rev. 1.00.00 Page 3 of 13

# 1 HIQuad X Operating System Version V13.2

This chapter describes the improvements, new functions and restrictions of the following HIQuad X operating system versions (V13.2) compared to the previous ones:

OS version	File name	Description
V13.2	HQXCPU51_HA1_OS_V13.2.ldb	Safety-related operating system for F- CPU 01 processor modules
V13.2	HQXCOM_HA1_OS_V13.2.ldb	Operating system for F-COM 01 communication modules

Table 1: Modified Operating System Versions

The operating system versions not mentioned in Table 1 are listed in the previous release notes.

HIMA recommends upgrading all modules to the current operating system version.

HI 803 245 E Rev. 1.00.00 Page 5 of 13

New Functions Release Notes

# 2 New Functions

The COM operating systems offer OPC UA Server functionality.
The CPU operating systems have been extended with an interface for the OPC UA Server to enable access to system events.

The OPC UA Server functionality requires its own license.

Page 6 of 13 HI 803 245 E Rev. 1.00.00

# 3 Firmware Improvements

 After a reload, the SOE function did not report the first occurrence of a scalar event threshold being exceeded to the X-OPC Server. This problem was fixed in processor module operating system V13 (HIMatrix V17).

HI 803 245 E Rev. 1.00.00 Page 7 of 13

Firmware Restrictions Release Notes

## 4 Firmware Restrictions

 In very seldom cases, if one or more communication protocols such as Modbus or ComUserTask are used under load control and the controller or COM module changes from RUN to STOP, the COM module may reboot.

- Restriction with respect to reload licenses: Features that are used in a COM module with a demo license, cannot be activated by performing a reload of the controller (CPU-Module) with a full license. The message displayed in the license management of the CPU module reports that a regular license is available, but a DEMO license is in use. This behavior occurs if no reload or cold reload is performed for the COM module itself.
  - The full license is only used and properly reported after a restart of the controller (CPU module), a reload or cold reload of the COM module.
- In redundant systems, only the value 1 may be selected for *Prio A&E*, or problems may occur during synchronization.

Page 8 of 13 HI 803 245 E Rev. 1.00.00

Release Notes References

## 5 References

- HIQuad X system manual (HI 803 211 E).
- HIQuad X safety manual (HI 803 209 E).
- Communication manual (HI 801 101 E).

#### 5.1 Zstandard License Terms

The CPU operating systems contain a Zstandard decompression algorithm provided with the following license terms:

**BSD License** 

For Zstandard software

Copyright (c) 2016-present, Facebook, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification,

are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name Facebook nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## 5.2 Apache License

The COM operating system includes an SSL/TLS library Mbed TLS licensed by ARM Limited.

http://www.apache.org/licenses/LICENSE-2.0

HI 803 245 E Rev. 1.00.00 Page 9 of 13

Release Notes Appendix

# **Appendix**

# **Index of Tables**

Table 1: Modified Operating System Versions

5

HI 803 245 E Rev. 1.00.00 Page 11 of 13

# **Release Notes**

# HI 803 245 E

For further information, please contact:

## **HIMA Paul Hildebrandt GmbH**

Albert-Bassermann-Str. 28 68782 Brühl, Germany

Phone: +49 6202 709-0 Fax +49 6202 709-107 E-mail: info@hima.com

Learn more about HIQuad X online:



www.hima.com/en/products-services